The Kernel Latency

Advanced Operating Systems

Luca Abeni

luca.abeni@santannapisa.it

Latency


- Latency: measure of the difference between the theoretical and actual schedule
 - Task τ expects to be scheduled at time t
 - ullet ... but is actually scheduled at time t'
 - \Rightarrow Latency L = t' t
- The latency L can be modelled as a blocking time \Rightarrow affects the guarantee test
 - Similar to what done for shared resources
 - Blocking time due to latency, not to priority inversion

Effects of the Latency

- Upper bound for L? If not known, no schedulability tests!!!
 - The latency must be bounded: $\exists L^{max} : L < L^{max}$
- If L^{max} is too high, only few task sets result to be schedulable
 - Large blocking time experienced by all tasks!
 - The worst-case latency L^{max} cannot be too high

Sources of Latency

- ullet $\,$ A task au_i is a stream of jobs $J_{i,j}$ arriving at time $r_{i,j}$
- Job $J_{i,j}$ is scheduled at time $t' > r_{i,j}$
 - $t' r_{i,j}$ is given by:
 - 1. $J_{i,j}$'s arrival is signalled at time $r_{i,j} + L^1$
 - 2. Such event is served at time $r_{i,i} + L^1 + L^2$
 - 3. $J_{i,j}$ is actually scheduled at $r_{i,j} + L^1 + L^2 + L^3$




Analysis of the Various Sources

- $L = L^1 + L^2 + L^3$
- L^3 is sometimes called *scheduler latency*
 - But it is not really a latency!!!
 - Interference from higher priority tasks
 - Already accounted for by RTA / TDA or similar → let's not consider it
- L^2 is the non-preemptable section latency (L^{np})
- ullet L¹ is due to the delayed interrupt generation

Non-Preemptable Section Latency

- Delay between time when an event is generated and when the kernel handles it
 - Due to non-preemptable sections in the kernel, which delay the response to hardware interrupts
 - Composed by various parts: interrupt disabling, bottom halves delaying, . . .
- Depends on how the kernel handles the various events...
- Will talk about it later!



Interrupt Generation Latency

- Hardware interrupts: generated by devices
- Sometimes, an interrupt should be generated at time t . . .
- ... but it si actually generated at time $t' = t + L^{int}$
- L^{int} is the *Interrupt Generation Latency*
 - It is due to hardware issues
 - It is *generally* small compared to L^{np}
 - Exception: if the device is a timer device, the interrupt generation latency can be quite high
 - ullet Timer Resolution Latency L^{timer}

The Timer Resolution Latency

- Interrupt generation latency for a hw timer device
- L^{timer} can often be much larger than the non-preemptable section latency L^{np}
- Where does it come from?
 - Kernel timers are generally implemented by using a hardware device that produces periodic interrupts
- Can we do anything about it?

Ticks and Timers

- Periodic timer interrupt → tick
- Example: periodic task (setitimer(), Posix timers, clock_nanosleep(), ...) τ_i with period T_i
 - Job end $\rightarrow \tau_i$ sleeps for the next activation
- Activations are triggered by the periodic interrupt
 - Periodic tick interrupt, with period T^{tick}
 - Every T^{tick} , the kernel checks if the task must be woken up
 - If T_i is not multiple of T^{tick} , τ_i experiences a timer resolution latency

The Periodic Tick

- Traditional operating systems: timer device programmed to generate a periodic interrupt
 - Example: in a PC, the Programmable Interval Timer (PIT) is programmed in periodic mode
- At every tick the execution enters kernel space
- The kernel executes and can
 - Wake up tasks
 - Adjust tasks priorities
 - Run the scheduler, when returning to user space
 - → possible preemption

Tick Tradeoff


- Timer interrupt period: trade-off between responsiveness (low latency) and throughput (low overhead)
- Large $T^{tick} \rightarrow$ large timer resolution latency
- Small $T^{tick} \rightarrow \text{high number of interrupts}$
 - More switches between US and KS
 - Tasks are interrupted more often
 - → Larger overhead

Trade-off Examples

- For non real-time systems, it is possible to find a reasonable tradeoff...
- But it still depends on the workload!
 - Desktop or server?
- Example: the Linux kernel
 - Linux 2.4: 10ms (HZ = 100)
 - Linux 2.6: HZ = 100, 250, or 1000
 - Other systems: $T^{tick} = 1/1024$

Timer Resolution Latency

ullet Experienced by all tasks that want to sleep for a specified time T



- τ_i must wake up at time $r_{i,j} = jT_i$
- But is woken up at time $t' = \left\lceil \frac{r_{i,j}}{T^{tick}} \right\rceil T^{tick}$

Timer Resolution Latency - Upper Bound

The timer resolution latency is bounded:

•
$$t = r_{i,j}$$
• $t' = \left\lceil \frac{r_{i,j}}{T^{tick}} \right\rceil T^{tick}$


• $L^{timer} = t' - r_{i,j} = \left\lceil \frac{r_{i,j}}{T^{tick}} \right\rceil T^{tick} - r_{i,j} = \left(\left\lceil \frac{r_{i,j}}{T^{tick}} \right\rceil - \frac{r_{i,j}}{T^{tick}} \right) T^{tick} \le T^{tick}$

Problems with Periodic Ticks

- Reducing T^{tick} below 1ms is generally not acceptable...
- ...So, periodic tasks can expect a blocking time due to L^{timer} up to 1ms
 - How large is the effect on the schedulability tests?
- Additional problems:
 - Tasks' periods are rounded to multiples of T^{tick}
 - Limit on the minimum task period: $\forall i, T_i \geq T^{tick}$
 - ...

Useless Timer Interrupts

 Additional problem: a lot of useless timer interrupts might be generated



Timers and Clocks

- Remember?
 - Timer: generate an event at a specified time t
 - Clock: keep track of the current system time
- A timer can be used to wake up a periodic task τ , a clock can be used to read the system time (gettimeofday())
- Timer Resolution
- Clock Resolution

Timer and Clock Resolution

- Timer Resolution: minimum interval at which a periodic timer can fire
 - If periodic ticks are used, the timer resolution is T^{tick}
- Clock Resolution: minimum difference between two different times returned by the clock
 - What's the expected clock resolution?

Clock Resolution

- Traditional OSs use a "tick counter"
 - Very fast clock: return the number of ticks (jiffies in Linux) from the system boot
 - Clock Resolution: T^{tick}
- Modern PCs have higher resolution time sources...
 - On x86, TSC (TimeStamp Counter)
 - High-Resolution clock: use the TSC to compute the time since the last timer tick...
- Summary: High-Resolution clocks are easy!
 - Every modern OS kernel provides them

Clock Resolution vs Timer Resolution

- Even using a "traditional" periodic timer tick, it is easy to provide high-resolution clocks
 - Time can be easily read with a high accuracy
- On the other hand, timer resolution is limited by the system tick T^{tick} (= 1 / HZ)
 - It is impossible to generate events at arbitrary instants in time, without latencies

Timer Devices

- Timer devices (ex: PIT i8254) generally work in 2 modes: periodic and one-shot
- Programmed writing a value C in a counter register
- The counter register is decremented at a fixed rate
- When the counter is 0, an interrupt is generated
 - If the device is programmed in periodic mode, the counter register is automatically reset to the programmed value
 - If the device is programmed in one-shot mode, the kernel has to explicitly reprogram the device (by setting the counter register to a new value)

Using the One-Shot Mode

- The periodic mode is easier to use! This is why most kernels use it
- When using one-shot mode, the timer interrupt handler must:
 - 1. Acknowledge the interrupt handler, as usual
 - 2. Check if a timer expired, and do its usual stuff...
 - 3. Compute when the next timer must fire
 - Reprogram the timer device to generate an interrupt at the correct time
- Steps 3 and 4 are particularly critical and difficult

Reprogramming the Timer Device - 1

- When the kernel reprograms the timer device (step
 4), it must know the current time...
- ...But the last known time is the time when the interrupt fired (before step 1)...
 - A timer interrupt fires at time t_1
 - The interrupt handler starts (enter KS) at time t_1'
 - Before returning to US, the timer must be reprogrammed, at time t_1''
 - Next interrupt must fire at time t_2 ; the counter register is loaded with t_2-t_1
 - Next interrupt will fire at $t_2+(t_1''-t_1)$

Reprogramming the Timer Device - 2

- The error described previously accumulates
- Risk: drift between real time and system time
- A free run counter (not stopped at t_1) is needed
- The counter is synchronised with the timer device \Rightarrow the value of the counter at time t_1 is known
- This permits to know the time $t_1'' \Rightarrow$ the new counter register value can be computed correctly
- On a PC, the second PIT counter, or the TSC, or the APIC timer can be used as a free run counter

High Resolution Timers

- Serious real-time kernels → High-Resolution Timers (use hw timer in one-shot mode)
 - Already implemented in RT-Mach
 - Also implemented in RTLinux, RTAI and others
- General-Purpose kernels are more concerned about stability and overhead
 - Too much overhead for general purpose kernels?
- Fixed: hrtimers are in Linux since version 2.6.21

HRT and Timer Ticks


- Compatibility with "traditional" kernels:
 - The tick event can be emulated through high-resolution timers
 - ⇒ Timer device programmed to generate interrupts both:
 - When needed to serve a timer, and
 - At tick boundaries
- ...But the "tick" concept is now useless
 - Tickless (or NO_HZ) system
 - Good for saving power

Non-Preemptable Section Latency

- The non-preemptable section latency L^{np} is given by the sum of different components
 - Interrupt disabling
 - 2. Delayed interrupt service
 - Delayed scheduler invocation
- The first two are mechanisms used by the kernel to guarantee the consistency of internal structures
- The third mechanism is sometimes used to reduce the number of preemptions and increase the system throughput

Disabling Interrupts

 Remember? Before checking if an interrupt fired, the CPU checks if interrupts are enabled...



Every CPU has some protected instructions
 (STI/CLI on x86) for enabling/disabling interrupts

Interrupts and Latency

- In modern system, only the kernel (or code running in KS) can enable/disable interrupts
- Interrupts disabled for a time $T^{cli} \rightarrow L^{np} \geq T^{cli}$
- Interrupt disabling is used to enforce mutual exclusion between sections of the kernel and ISRs

Delayed Interrupt Service - 1


- When the interrupt fires, the ISR is ran, but the kernel can delay interrupt service some more...
 - ISRs are generally small, and do only few things
 - An ISR can set some kind of software flag, to notify that the interrupt fired
 - Later, the kernel can check such flag and run a larger (and more complex) interrupt handler
- Hard IRQ handlers (ISRs) vs "Soft IRQ handlers"

Delayed Interrupt Service - 2


- Advantages of "soft IRQ handlers":
 - ISRs generally run with interrupts disabled,
 - Soft IRQ handlers can re-enable hardware interrupts
 - Enabling/Disabling soft handlers is simpler/cheaper
- Disadvantages:
 - Increase NP latency: $L^{np} >> T^{cli}$
 - "Soft IRQ handlers" are often non-preemptable increasing the latency for other tasks too...

Deferred Scheduling

- Scheduler invoked when returning from KS to US
- Sometimes, return to US after a lot of activities
 - Try to reduce the number of KS ↔ US switches
 - Reduce the number of context switches
 - Throughput vs low latency
- ISR executed at the correct time, soft IRQ handler ran immediately, but scheduler invoked too late



Latency in the Standard Kernel



Summing Up - 1

- ullet L^{np} depends on some different factors
- In general, no hw reasons \rightarrow it almost entirely depends on the *kernel structure*
 - Non-preemptable section latency is generally the result of the strategy used by the kernel for ensuring mutual exclusion on its internal data structures

Summing Up - 2

- To analyze / reduce L^{np} , we need to understand such strategies
- Different kernels, based on different structures, work in different ways
- Some activities causing L^{np} :
 - Interrupt Handling (Device Drivers)
 - Management of the parallelism

Example: Data Structures Consistency

- HW interrupt: breaks the regular execution flow
 - If the CPU is executing in US, switch to KS
- If execution is already in KS, possible problems:
 - 1. The kernel is updating a linked list
 - 2. IRQ While the list is in an inconsistent state
 - 3. Jump to the ISR, that needs to access the list...
- Must disable interrupts while updating the list!
- Similar interrupt disabling is also used in spinlocks and mutex implementations...